




# Using VPN with iPad or iPhone

## How to Install an iPad/iPhone VPN Profile


1. Ensure you are connected to WiFi or 3G.
2. Open your web browser.
3. Navigate to <http://www.anl.gov/employees/working-remotely/virtual-private-network-vpn-client> and click on "VPN Client Downloads."




4. Enter your ANL domain username and password (no anl\ prefix needed).



- Click on "Mobile Configuration" next to the iPad and iPhone option.



- Click "Install."



7. Enter your device passcode here (If one has been established) to continue.




(screen with passcode established)

8. Enter your ANL domain username and click "Next."



9. Enter your ANL domain password and click "Next."  
(CryptoCard users should enter that password here.)



10. You will then see "Profile Installed." Click "Done."




(my screen showing VPN already)

## How to Establish a VPN Connection

1. Click Settings and turn on VPN. You will see VPN connecting.



2. Enter your ANL domain account and password ,and click "Ok."  
(CryptotoCard users should enter that password here.)




3. Click "OK" to the ANL VPN disclosure. You are now connected and should see a VPN box at the top left of your screen.



## How to Connect Remotely to Your Work Computer with an iPad or iPhone

1. You must be connected to WiFi and VPN before you can Remote Desktop to your work computer.
2. Open the App Store, type "RDP" in the search box, and click "Enter." Make sure your VPN is turned OFF at this point. Otherwise, you will get an error to launch App Store.



(screen when VPN is ON.)

3. Click either
  - a. Remote Desktop Lite –RDP (Free) Note: This version does not support a pointer (mouse) feature. OR
  - b. Remote Desktop – RDP (\$5.99) You will need to purchase (out of your pocket) and install this app if you would like the pointer (mouse) feature and more.






4. Install the selected app using your personal iTunes account username and password.



5. Open the RDP app. Click Menu and Edit Connections.



- Click on a blank host name and enter the CSI number for your work computer (CS1xxxxxx.division.anl.gov) and click Connect. (See [Using Remote Desktop](#) to find out how to obtain your host name.)

Host List Connection Connect

Windows Workstation IP address

cs1xxxxxx.division.anl.gov

Either a DNS name or a raw IP address as 192.168...

Windows Workstation Port

3389

Default port is 3389

User (optional)

<enter user ID/Name>

User ID for the Windows PC

Q W E R T Y U I O P

A S D F G H J K L Done

↑ Z X C V B N M ! ? ↑

.?123 .?123

7. The connection will be established, and you will see the ANL disclaimer. Click OK and you will see the login or unlock screen from your work computer. Enter your ANL domain username and password to gain access.

